





Instructions Resetting CMAST local client database (CMDOP.CDF) file

Windows 7 & Windows 10:

- Close CMAST.
- Make sure Folders are Unhidden.
 1. **Open the "Folder Options" menu.** To do this, first click on the "Start" button. In the menu that appears, click on "Control Panel." From the "Control Panel," click on "Folder Options."




2. **When the Folder Options menu opens, click on the tab that reads "View."**






Instructions Resetting CMAST local client database (CMDOP.CDF) file

3. **Enable the setting to show hidden files on your computer.** Scroll down until you see an option called "Hidden Files and Folders." There are 2 radio buttons listed underneath this entry; click on the one that reads "Show hidden files, folders, and drives." Select "OK".



- Within a Windows Explorer, please navigate to C://ProgramData/CMAST



- Either save your current CMDOP.CDF file to another location or rename it. It is recommended to save it to a different location as the uninstall/reinstall of CMAST resets this folder and all information may be lost.
- With every install of CMAST, there is a CMDOP_Blank.CDF file. Now copy this file.
- Paste it within the same folder and rename it to CMDOP.CDF
- Launch the CMAST application. The application should be empty (no frames/glazing/spacers/assemblies/products/projects).